


Ver los métodos estáticos de la clase [System.Console] desde PowerShell

[System.Console] Representa los flujos de entrada, salida y error estándar para las aplicaciones de consola. Esta clase no puede heredarse.

[crayon-6a9d7a45b562f328771044/]



```
Windows PowerShell ISE (x86)
Archivo Editar Ver Herramientas Depurar Complementos Ayuda
Sin titulo1.ps1 Sin titulo2.ps1 Sin titulo3.ps1
1 [System.Console] | Get-Member -Static -MemberType Method
2 [System.Console]::Beep()

-----
Beep                Method      static void Beep(), static void Beep(int frequency, int duration)
Clear               Method      static void Clear()
Equals              Method      static bool Equals(System.Object objA, System.Object objB)
MoveBufferArea      Method      static void MoveBufferArea(int sourceLeft, int sourceTop, int sourceWidth, ...
OpenStandardError   Method      static System.IO.Stream OpenStandardError(), static System.IO.Stream OpenSt...
OpenStandardInput    Method      static System.IO.Stream OpenStandardInput(), static System.IO.Stream OpenSt...
OpenStandardOutput   Method      static System.IO.Stream OpenStandardOutput(), static System.IO.Stream OpenS...
Read                Method      static int Read()
ReadKey             Method      static System.ConsoleKeyInfo ReadKey(), static System.ConsoleKeyInfo ReadKe...
ReadLine            Method      static string ReadLine()
ReferenceEquals      Method      static bool ReferenceEquals(System.Object objA, System.Object objB)
ResetColor           Method      static void ResetColor()
SetBufferSize        Method      static void SetBufferSize(int width, int height)
SetCursorPosition   Method      static void SetCursorPosition(int left, int top)
SetError             Method      static void SetError(System.IO.TextWriter newError)
SetIn                Method      static void SetIn(System.IO.TextReader newIn)
SetOut              Method      static void SetOut(System.IO.TextWriter newOut)
SetWindowPosition    Method      static void SetWindowPosition(int left, int top)
SetWindowSize        Method      static void SetWindowSize(int width, int height)
Write                Method      static void Write(string format, System.Object arg0), static void Write(str...
WriteLine            Method      static void WriteLine(), static void WriteLine(bool value), static void Wri...
```